

EMail

电子邮件(E-mail)

SMTP服务器: smtp.qq.com 端口: 465(SSL加密)

IMAP服务器: imap.qq.com 端口: 993(SSL加密)

POP3服务器: pop.qq.com 端口: 995(SSL加密)

SMTP

POP

IMAP

Webmail

下载Roundcube <https://roundcube.net/download/>

浏览器访问<http://localhost/webmail/installer.php>

postfix

```
sudo apt update
sudo apt install postfix
sudo dpkg-reconfigure postfix
General type of mail configuration: Internet Site
NONE doesn't appear to be requested in current config
System mail name: example.com
Root and postmaster mail recipient: <admin_user_name>
Other destinations for mail: server1.example.com, example.com,
localhost.example.com, localhost
Force synchronous updates on mail queue?: No
Local networks: 127.0.0.0/8
Yes doesn't appear to be requested in current config
Mailbox size limit (bytes): 0
Local address extension character: +
Internet protocols to use: all
```

#方法二

```
sudo vi /etc/postfix/main.cf
myhostname = example.com
alias_maps = hash:/etc/postfix/virtual
```

dovecot

```
sudo apt install dovecot-core dovecot-imapd dovecot-pop3d

sudo vi /etc/dovecot/dovecot.conf
protocols = imap pop3
sudo vi /etc/dovecot/conf.d/10-mail.conf
mail_location = maildir:~/Maildir
sudo vi /etc/dovecot/conf.d/10-auth.conf
disable_plaintext_auth = no
auth_mechanisms = plain login
!include auth-system.conf.ext
sudo systemctl restart dovecot
```

Roundcube

依赖

```
sudo apt install mariadb-server unzip
sudo apt install php php-mysql php-gd php-mbstring php-xml php-intl php-curl
```

sql

```
sudo mysql -u root -p
CREATE DATABASE roundcubemail DEFAULT CHARACTER SET utf8 COLLATE
utf8_general_ci;
GRANT ALL PRIVILEGES ON roundcubemail.* TO 'roundcube'@'localhost'
IDENTIFIED BY 'your_strong_password';
FLUSH PRIVILEGES;
EXIT;
```

nginx

```
server {
    listen 80;
    server_name mail.example.com;

    root /var/www/roundcube;
    index index.php;

    location ~ \.php$ {
        include snippets/fastcgi-php.conf;
```

```
    fastcgi_pass unix:/run/php/php8.2-fpm.sock;
    fastcgi_param SCRIPT_FILENAME $document_root$fastcgi_script_name;
    include fastcgi_params;
}

location ~ /\.ht {
    deny all;
}

location ~ ^/(config|temp|logs)/ {
    deny all;
}
}
```

部署

```
cd /var/www/
wget
https://github.com/roundcube/roundcubemail/releases/download/1.6.9/roundcube
mail-1.6.9-complete.tar.gz
tar -xzf roundcubemail-1.6.9-complete.tar.gz
mv roundcubemail-1.6.9 roundcube
chown -R www-data:www-data /var/www/roundcube
访问 http://mail.example.com/installer 按向导操作：
```

Database setup: 填入之前创建的 roundcubemail 数据库信息

IMAP Settings:

IMAP Host: ssl://localhost 或 tls://localhost

Port: 993

SMTP Settings:

SMTP Host: tls://localhost

Port: 587

Use SMTP authentication:

Username: %u Password: %p

From:

<https://sujj.wiki/> - 落月思君归

Permanent link:

<https://sujj.wiki/doku.php?id=%E8%BD%AF%E4%BB%B6:email>

Last update: **2026/01/02 00:57**

