

Dolibarr

```
-- 创建数据库 (使用 UTF8 编码)
CREATE DATABASE dolibarr WITH OWNER = postgres ENCODING = 'UTF8' LC_COLLATE
= 'en_US.UTF-8' LC_CTYPE = 'en_US.UTF-8' TEMPLATE = template0;

-- 创建专用用户 (可选, 更安全)
CREATE USER dolibarr_user WITH PASSWORD 'your_secure_password';
GRANT ALL PRIVILEGES ON DATABASE dolibarr TO dolibarr_user;

-- 退出
\q
```

```
server {
    listen 80;
    server_name erp.yourdomain.com; # 替换为你的域名或服务器 IP

    # root /var/www/dolibarr;
    root /var/www/html/htdocs;
    index index.php index.html;

    # 安全：禁止访问敏感目录
    location ~ ^/(conf|documents|install|scripts|test|vendor)/ {
        deny all;
        return 403;
    }

    # PHP 处理
    location ~ \.php$ {
        include snippets/fastcgi-php.conf;
        fastcgi_pass unix:/run/php/php8.2-fpm.sock;
        fastcgi_param SCRIPT_FILENAME $document_root$fastcgi_script_name;
        include fastcgi_params;
    }

    # 静态资源缓存
    location ~* \.(js|css|png|jpg|jpeg|gif|ico|svg)$ {
        expires 1y;
        add_header Cache-Control "public, immutable";
    }

    # 重写规则 Dolibarr 支持 PATH_INFO
    location / {
        try_files $uri $uri/ /index.php?$query_string;
    }
}
```

```
cd /var/www
sudo wget
https://github.com/Dolibarr/dolibarr/archive/refs/tags/20.0.1.tar.gz
sudo tar -xzf 20.0.1.tar.gz
```

```
sudo mv dolibarr-20.0.1 dolibarr
```

```
sudo chown -R www-data:www-data /var/www/html/htdocs/
```

```
sudo chmod -R 755 /var/www/html/htdocs/
```

指向的目录root dolibarr/htdocs

创建一个空文件并为你的网页服务器用户设置写权限（安装完成后写权限将被移除）

```
touch htdocs/conf/conf.php
```

```
cd /var/www/html/htdocs/conf
```

```
cp conf.php.example conf.php
```

从浏览器中，进入dolibarr的“安装/”页面

URL取决于你的网页配置如何指向你的dolibarr安装。它可能看起来像：

<http://localhost/dolibarr/htdocs/install/>

<http://localhost/dolibarr/install/>

<http://yourdolibarrvirtualhost/install/>

From:

<https://sujj.wiki/> - 落月思君归

Permanent link:

<https://sujj.wiki/doku.php?id=%E8%BD%AF%E4%BB%B6:dolibarr&rev=1765550585>

Last update: **2026/01/02 02:08**

